# Mapping Features Built Into Order Entry System

All of the JMK mapping features utilize various public interfaces built into Google Maps, which ensures that these maps will always be current and available from any Internet connection.

I.      Directions

    A.      Current Location
         Use the command  **MAP**  from within a work order

         Uses the Customer shipping address to display a map on your web browser of that address.

    B       Directions
         Use the command  **DIR**  from within a work order

         Uses the store location and the customer shipping address to create a map showing driving directions between these two locations.

II.     Automatic Computation of Delivery / Mileage Charges

    A.      User definable charge options to enable automatic entry of charges on an invoice.

    B.      Uses an item setup in inventory to define the amount to charge per mile and the  **DIR**  feature of Google maps (store locations to customer location) to get the mileage used to compute the charge.

# I. A Sample Map
## Map of location

Marketing Aids

# I. B Sample Map
## Map of directions

## II. A Automatic computation of delivery charge.

### Add desired delivery charge item to work order

```
oemnu -                                          /dsk0/010013
Ord     WB05236   Loc.: BLM │Dft Sp:JMK Cp:JMK Ip:---│ A/R#: 99-BLM
P/O#                  TPMS │01 CHEVY SILVERADO       │ FET..: Y    A/Crd:  -32
GRAZIE RISTORANTE &        │C1500 4X2 EXT LONG BX    │ TxCod: IB

 L#    Part #              Description            Qt  BO  Sell      Ext $
 1│SASWEEP        ALIGN- ANGLE SWEEP               1   0  28.00      28.00
 2│DELCHG         PER MILE DELIVERY CHARGE        ....      0.25
 3
 4
 5
 6
 7
 8
 9
10
11

System will figure the distance from this STORE location to:
   1050 E OAKTON ST DES PLAINES, IL 60018

Press ENTER only, to accept this address or N to enter an alternate


                                            30-Sep-2009 01:24 PM
```

### Accept to address or optionally change

```
11│
Delivery to:
 1050 E OAKTON ST DES PLAINES, IL 60018
Mileage: 160, est. travel time: 2H 48Min



                                            30-Sep-2009 01:24 PM
```

### Press enter to confirm and charge is entered onto work order.

```
oemnu -                                          /dsk0/010013
Ord     WB05236   Loc.: BLM │Dft Sp:JMK Cp:JMK Ip:---│ A/R#: 99-BLM
P/O#                  TPMS │01 CHEVY SILVERADO       │ FET..: Y    A/Crd:  -32
GRAZIE RISTORANTE &        │C1500 4X2 EXT LONG BX    │ TxCod: IB

 L#    Part #              Description            Qt  BO  Sell      Ext $
 1│SASWEEP        ALIGN- ANGLE SWEEP               1   0  28.00      28.00
 2│DELCHG         PER MILE DELIVERY CHARGE        160   0  0.25      40.00t
 3               160 mi, est. travel: 2H 48min
 4│.............
 5
 6
 7
 8
 9
10
11

Enter Exact PART#, 'CC' to add a comment line, or lead char w/entry, to search

Leadoff Search Options:  (use double entry leadoff, for full screen display)
= - your PART#         - - Tire/Whl/Tube SIZE
# - mfg  PART#             (trail with = for    \ - DESCRIPTION, all words
                           equivalent sizes)  (trailing with =abcd limits
  (-- - default search leadoff char)            to only with that string)
                                            30-Sep-2009 01:24 PM
```

Marketing Aids

## II. B Setup inventory Item for delivery charge.

Item is defined by Class Code as a delivery charge item

```
oe002.run -                                    /dsk0/010013
 1) ITEM Number.: DELCHG                        Loc: Common Scr: 1
                        Inventory Master File
 2) Description.: PER MILE DELIVERY CHARGE   ┌[ Cross Reference Data ]─┐
 3) Product Type: L   - LABOR- Misc          │                         │
 4) Manuf ITEM#.:                            │                         │
 5) Manuf Code..:       - (not on file)      │                         │
 6) Model.......:                            │                         │
 7) Item SEQ#...:   0                         │                         │
 8) Weight......:   0.000 Lbs.               │                         │
 9) Stock TYPE..: STOCK ITEM                 └──────── BLM Loc ────────┐
10) Class code..: M                           │QTY                      │
                                              │On Hnd: +++++   Comm:  3714│
11) Quote Comm't 1:                           │BO+Est:     0  OpnPO:    0│
12) Quote Comm't 2:                           │COST (w/o FET)           │
13) Inv Comment 1.:            2:             │Avg$:     0.00 Last:   0.00│
                                              │Last Activity            │
                                              │Rcvd:         Sold:      │
18) LOC to edit.: BLM                         │TrIn:          Out:      │
                                              └─────────────────────────┘
OPTION: ▮
   ENTER only - Save changes    │          99 - Goto 2nd scr
            XX - Cancel changes  │          S1-S5 - Goto S#
            HH - Help            │          A1-A4 - Goto A#
             # - Select field    │
                                       30-Sep-2009 01:38 PM
```

Pricing is defined just like any other item in inventory with all pricing and discounting features available.

```
oe002.run -                                    /dsk0/010013
I#: DELCHG - PER MILE DELIVERY CHARGE          Loc: BLM Scr: 3
                        Inventory Pricing
 1) RETAIL Price:     0.2500 11) 08/25/08
 2) COMMER Price:     0.1900 12) 08/25/08 |20) Flat Rate...:  0.00
 3) WHOLES Price:     0.0000 13)
 4) BASE Price..:     0.0000 14)
 5) LIST Price..:     0.0000 15)
 6) ADJUSTM'T Pr:     0.0000 16)
COSTS
 7) Last........:     0.0000 Dt:
 8) Avg$ w/o fet:     0.0000          TRACKING
 9) Standard....:     0.0000 19)  |ORG Qty:        Cst:   0.00
                                   |                FET:   0.00
40) QTY   OH: 999,999    Cm:  3,714
          BO+E:      0   OnO:     0  |30) Enable..: Y   08/25/08
          Rs:       0                |31) A/R Acct: Y
41) Reordr Pt:      0   Qty:      0
42) Movement Ind: A

OPTION:
   ENTER only - Save changes  | #= - Edit all loc  |   99 - Goto 4th scr
            XX - Cancel changes |    fld #1=>9      | S1-S5 - Goto S#
            HH - Help           |    fld #40=>42    | A1-A4 - Goto A#
             # - Select field   |
                                       30-Sep-2009 01:38 PM
```